

## Change / Delete Batch

### Use

This activity is used to change / delete a batch.

### Procedure

1. Access the transaction using following navigation options:

<b>SAP ECC Menu</b>	<i>Logistics → Materials Management → Material Master → Batch → Change</i>
<b>Transaction code</b>	<b>MSC2N</b>

2. On **Create Batch Screen**, make the following entries:

Field Name	User action and values	Comment
Material	Required	Alphanumeric key uniquely identifying the material.
Batch	Required	Assigns a material that is manufactured in batches or production lots to a specific batch.
Plant	Required	Key uniquely identifying a plant.
Stor. Location	Required	Number of the storage location at which the material is stored. A plant may contain one or more storage locations.


**Change Batch**

Material: FG00049  
Batch: BP02BATCH  
Plant: BP02  
Stor. Location: 0001

Basic data 1 | Basic data 2 | Classification | Material data | Changes

3. Press **Enter** key.
4. On **Change Batch Screen**, tick **Batch Deletion Flag at a Plant** and **Deletion Flag Batch Stock**.

## Change Batch



Material:       FG-MIXPLANT C.HAM(VISMIN) .250K  
 Batch:   
 Plant:       Valenzuela 2 (P2)  
 Stor. Location:       FG - FPM Non-WMM

Basic data 1 | Basic data 2 | Classification | Material data | Changes

**Expiration Date**

Production Date:

Shelf Life Exp. Date:

Available From:

Period Indicator:

**Miscellaneous**

Next Inspection:        Batch Deletion Flag

Batch Deletion Flag at a Plant  
 Deletion Flag Batch Stock

Phys. Inv. Block:

**Trading Data**

Vendor:       Ctry of origin:

Vendor Batch:       Reg. of origin:


Last Goods Receipt:       Exp/imp group:



**Batch Deletion Flag at a Plant** indicator that flags for deletion all the data on a batch at plant level. The reorganization program checks whether deletion is allowed. If it is the batch data in this plant and all subordinate storage locations is deleted.



**Deletion Flag Batch Stock** indicator the flags for deletion all data on a batch at storage location level. The reorganization program checks whether deletion is allowed and, if it is, deletes the data.

5. Click **Save**  icon to save the change / delete batch.

### Result

Batch for the material has been change / delete.

Changing batch BP02BATCH



To view the change / delete batch.

1. To view the change / delete batch access the transaction using following navigation options:

<b>SAP ECC Menu</b>	<i>Logistics → Materials Management → Material Master → Other → Stock Overview</i>
<b>Transaction code</b>	<b>MMBE</b>

2. On **Stock Overview: Company Code / Plant / Storage Location / Batch Screen**, make the following entries:

Field Name	User action and values	Comment
Material	Required	Alphanumeric key uniquely identifying the material
Plant	Required	Key uniquely identifying a plant.
Stor. Location	Required	Number of the storage location at which the material is stored. A plant may contain one or more storage locations.
Batch	Required	Assigns a material that is manufactured in batches or production lots to a specific batch.

3. Click **Execute**  icon or press **F8**.

4. On **Stock Overview: Basic List Screen**, notice that your created batch has mark **X** in **Del. Flag**.

**Stock Overview: Basic List**

Selection

Material: EG00049 G-MIXPLANT C.HAM(VISMIN) .250K  
 Material Type: FERT Finished Product  
 Unit of Measure: PAC Base Unit of Measure: PAC

Stock Overview

Client/Company Code/Plant/Storage Location/Batch/Special Stock | Del. Flag | Unrestricted use | Qual. inspection | Reserved | Rcpt r...

Full		1,792.000			
BP01 CDO Foodsphere, Inc.		1,792.000			
BP02 Valenzuela 2 (P2)		1,792.000			
0001 EG - FPM Non-WMM		1,792.000			
BP02BATCH	X				



**Del. Flag** is the general deletion flag.